

API Commands

ESPLUX

Demonstration Unit

Board Revision: 0.1

2015-07-27

What's this?

This is a list of commands you can use to control your ESPLux. They will be the same commands I use in controlling the light from OpenHAB, however, you can use these in any system you'd like.

Commands

The method of interacting with the ESPLux is rather simple. You send it an HTTP GET command, and it'll do what you ask, or return the information you need.

Light Control

*[/setlight.lua?val=**value**](#)*

<i>value</i>	0 – 1023	This is the light level you want to set. 0 is off, 1023 is 100% on, and any value in between is dimmed appropriately. Be aware that extremely low dim levels may not play nicely with some lights with smarts in them.
---------------------	----------	--

Indicator Lights

`/setIndicator.lua?state=value`

value	on - off	This is where you set the state of the indicator lights. The text 'on' or 'off' switches them on or off respectively.
--------------	----------	---

Current State

`/getState.lua`

This will return all of the configurable options in a flat text file. Each newline (\n) represents the next config value.

Line 1	0 – 1	This is the Light is dimmable checkbox. If it is 1, control on the web page for dimming is enabled. If it is 0, only on/off control is available. Note: This does <i>*not*</i> restrict the value you can send through on the Light Control section. Please use this value to determine what you send through.
--------	-------	---

Line 2	0 – 1	This is the Set light to previous value when switch is flipped checkbox. When it is set to 0, it will always start the light back at 1023 on power on. When set to 1, it will use the value set on Line 4
Line 3	<i>Text</i>	This is the name of the light set on the Light Name option.
Line 4	0 – 1023	This is the current light value set by the Light Control section above. This value is used to set the web page up with the appropriate value, also, is used in conjunction with Line 2 to set the appropriate state on AC On
Line 5	0 – 1	This is the Set Static IP checkbox. If it is set to 0, the light will use DHCP to obtain an IP address, and lines 6 – 8 are ignored. If it is set to 1, a static IP is set with the following settings.
Line 6	<i>IP Address</i>	This is the static IP address set in the interface
Line 7	<i>IP Address</i>	This is the subnet set in the interface
Line 8	<i>IP Address</i>	This is the gateway set in the interface